





“USB 2.0 TO RS232 ” DÖNÜŞTÜRÜCÜSÜNÜN KULLANILMASI

- Dönüştürücü USB girişlerinden birine takılır.
- Dönüştürücü ile gelen yazılımı CD ROM sürücüsüne takınız ve programı yükleyiniz.
- Denetim Masası >Sistem ve Bakım > Aygıt yöneticisi > Donanımlar ve Aygıtları görüntüle,





- Bağlantı Noktaları (COM ve LPT!) den USB Serial Port' u Tıkla,



- "Port Setting" I Tıkla > "Advanced" I Tıkla > COMPORT NUMBER seceneğinden COM2 olarak ayarlayınız.
(veya istediğiniz bir PORT olarak numaralandırabilirsiniz.)

Advanced Settings for COM2

COM Port Number: **COM2**

OK
Cancel
Defaults

USB Transfer Sizes

Select lower settings to correct performance problems at low baud rates.
Select higher settings for faster performance.

Receive (Bytes): 4096
Transmit (Bytes): 4096

BM Options

Select lower settings to correct response problems.

Latency Timer (msec): 16

Timeouts

Minimum Read Timeout (msec): 0
Minimum Write Timeout (msec): 0

Miscellaneous Options

Serial Enumerator
Serial Printer
Cancel If Power Off
Event On Surprise Removal
Set RTS On Close
Disable Modem Ctrl At Startup